



# Remote registry service installation on Windows 9x computers

## 1. Set the Access Control level




Get into the *Control Panel* and click on the *Network* icon.




Get into the “*Access Control*” tab, check “*User-Level access control*” and enter the name of the domain that will provide the list of users who will have access to this computer. Click *Ok*.

## 2. Enable remote administration

Remote administration should be enabled automatically after the previous step. So if you prefer, you can go directly to the third step.




To activate *remote administration* on the computer click on the *Password* icon in the *Control Panel*.




Check “*Enable remote administration on this server*” and in the *Administrators* list add the “*Domain admins*” group.


### 3. Install the Remote Registry service




In the network panel, get into the configuration tab and click *Add*.




Select *Service* and click *Add*.




Click "Have disk".




Insert the Windows 95/98 CD-ROM, enter the path to the "Microsoft Remote Registry" service .inf file ("win98\tools\reskit\netadmin\remotereg") and click *Ok*.




Click *Ok* to confirm the location



Click *Ok* to confirm that you want install the service.



Check that “*Microsoft Remote Registry*” has been added and click *Ok*.



The service will be working only after a reboot.

## 4. Ensure remote access is working properly

Log on to a Windows NT/2000/XP computer with a domain admin account and try to connect to the registry of your Windows 9x computer with `regedit` (doesn't work with NT 4) or `regedt32`.

With `regedit`: *Registry > Connect Network Registry*

With `regedt32`: *Registry > Select a computer*